
Nervousnet Mobile API's

How-To build an Android Native Axon App

- **Overview**

This document specifies a How-To step-by-step guide of integrating the nervousnet Mobile Library into your Android Project to use the Mobile API's.

A Nervousnet Axon Android application is any Android App that uses the nervousnet Mobile API's to access sensor and other related data from Nervousnet Mobile application.

- **Prerequisites**

Since nervousnet Mobile APIs is based on the Android Services and Android Interface Definition Language (AIDL) it would be good to read and understand how it works at:

<https://developer.android.com/guide/components/services.html>

<https://developer.android.com/guide/components/aidl.html>

For using the nervousnet mobile API's requires calling a remote interface defined with AIDL

<https://developer.android.com/guide/components/aidl.html#Calling>

- **Tools**

- Android Studio

- **JavaDoc**

<https://github.com/nervousnet/nervousnet-android/tree/master/Documents/Technical/Android/APIs>

- Click on index.html to launch the API documentation in your browser.
- NervousnetRemote Interface lists all API's that can be used by External Apps.

- **Source Code**

- 1) Nervousnet Project

<https://github.com/nervousnet/nervousnet-android>

- 2) Nervousnet Library Project (nervousnetLIB)

<https://github.com/nervousnet/nervousnet-android/tree/master/MobileClients/Android/nervousnet/nervousnetLIB>

3) Sample Extension Project (LightMeter, Accelerometer & Noisemeter)

(Inside GitHub project -> Mobile Clients -> Android -> Sample Extensions -> *)

<https://github.com/nervousnet/nervousnet-android/tree/master/MobileClients/Android/SampleExtensions/Lightmeter>

<https://github.com/nervousnet/nervousnet-android/tree/master/MobileClients/Android/SampleExtensions/Accelerometer>

<https://github.com/nervousnet/nervousnet-android/tree/master/MobileClients/Android/SampleExtensions/Noisemeter>

• Steps

- 1) Include the *nervousnetLIB* project as a library project of your Android project.

In Android Studio,:

- build.gradle (Project) add:

```
repositories {  
    jcenter()  
}
```

- build.gradle (Module) add:

```
dependencies {  
    compile 'ch.ethz.coss.nervousnet:nervousnetLIB:0.7.35'  
}
```

**The latest version of the nervousnetLIB can be found at:

<http://jcenter.bintray.com/ch/ethz/coss/nervousnet/nervousnetLIB/>

- 2) In the manifest file of your Android project define the Nervousnet Permissions:

```
<uses-permission android:name="ch.ethz.coss.nervousnet.hub.BIND_PERM" />
```

(Note: On some Android Devices using OS 6.0, after installing your Android App/axon, please enable the Bind Perm settings of your App manually from the device settings -> Application Manager -> App Permissions)

- 3) In your main activity implement

Interface NervousnetServiceConnectionListener and its methods

```
public void onServiceConnected();
```

```
public void onServiceDisconnected();
```

```
public void onServiceConnectionFailed(ErrorReading errorReading);
```

- 4) To connect to the Nervousnet Service

```
nervousnetServiceController = new NervousnetServiceController(YOURACTIVITY.this, this);  
nervousnetServiceController.connect();
```

- 5) Once the service is connected a callback is received inside the method

```
onServiceConnected()
```

- 6) To disconnect from the nervousnet Service call:

```
nervousnetServiceController.disconnect();
```

- 7) Once your app is connected to the Nervousnet Service you can use the methods to request for sensor data:

- ***SensorReading* getLatestReading(long sensorType);**
- ***void* getReading(long sensorType, RemoteCallback cb);**
- ***void* getReadings(long sensorType, long startTime, long endTime, RemoteCallback cb);**

NOTE: Please look into the Sample Axons Project for Lightmeter to understand a sample implementation

• Google Play Store Links:

- 1) Nervousnet Mobile App

<https://play.google.com/store/apps/details?id=ch.ethz.coss.nervousnet.hub>

- 2) Nervousnet – Sample Native Axon App List

LightMeter: <https://play.google.com/store/apps/details?id=ch.ethz.coss.nervousnet.extensions.lightmeter>

NoiseMeter: <https://play.google.com/store/apps/details?id=ch.ethz.coss.nervousnet.extensions.noisemeter>

Accelometer: <https://play.google.com/store/apps/details?id=ch.ethz.coss.nervousnet.extensions>.